



FacetWin SMB Share Connections

Requirements:

You must be using FacetWin Version 40q (Build 488) or later on the Linux/Unix server, This contains the latest improvements for working with Windows Vista and newer operating systems. Must upgrade to the [current FacetWin release](#) to take advantage of the latest improvements and optimizations.

DO NOT UNINSTALL!! Just install right over the current version.

The Problem:

Many FacetWin users find that upgrading to Windows Vista and newer operating systems will cause problems with SMB connections to the UNIX server FacetWin shares.

SMB connections to the UNIX server:

On the Windows PC, TCP/IP Properties, "Enable WINS" with the UNIX server's IP address and "Enable NetBIOS over TCP/IP".

FacetWin NTLMSSP and RHOST security methods should work for Windows Vista and newer operating systems using the default LAN Manager authentication level without making any changes to the Windows-side to connect to the UNIX server.

NTLMSSP Security Method:

To use the NTLMSSP method with FacetWin set `pass_security=NTLMSSP`. All of the other `pass_security` lines should be commented out. Run `fct_encrypt -b` on the UNIX server. The user's Windows PC password must be set in the `fctpasswd` file by running `fct_encrypt username` for each user. Remember to run this command anytime the user's Windows PC's password changes.

RHOST Security Method:

To use the RHOST method with FacetWin set pass_security=RHOST.
All of the other pass_security lines should be commented out.
The RHOST security method is not used very often, because it requires fixed IP addresses and a clear understanding of the "/etc/hosts", "\$HOME/.rhosts" and "/etc/hosts.equiv" files. For information on these files see the UNIX man pages for hosts, hosts.equiv and rhosts.

The PC names must be resolvable by the UNIX system.

UNIX Security Method:

To use UNIX security method with FacetWin set pass_security=UNIX.
All of the other pass_security lines should be commented out.

Administrative Tools
Local Security Policy
Local Policies
Security Options
Microsoft network client: Send unencrypted passwords to third-party SMB servers: Enabled

Network security: LAN Manager authentication level:
Send LM & NTLM - use NTLMv2 session security if negotiated

Registry entry if Microsoft Windows Home Edition:

```
[HKEY_LOCAL_MACHINE\System\CurrentControlSet\Services\LanmanWorkStation\parameters]"EnablePlainTextPassword"=dword:00000001
```

```
[HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\Lsa]  
"LmCompatibilityLevel"=dword:00000001
```

Apply change and then reboot Windows computer.

LANMAN Security Method:

To use the LANMAN method with FacetWin set `pass_security=LANMAN`.
Run `fct_encrypt -b` on the UNIX server. The user's Windows PC password must be set in the `fctpasswd` file by running `fct_encrypt username` for each user.
Remember to run this command anytime the user's Windows PC's password changes.
To change to the LAN Manager authentication security level on Windows PC:

Administrative Tools

- Local Security Policy

 - Local Policies

 - Security Options

 - Network security: LAN Manager authentication level:

 - Send LM & NTLM - use NTLMv2 session security if negotiated

Registry entry if Microsoft Windows Home Edition:

```
[HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\Lsa]
"LmCompatibilityLevel"=dword:00000001
```

Apply change and then reboot Windows computer.

NT SERVER Security Method:

In the `facetwin.cfg` configuration file, the NT SERVER security method is indicated by the line:

```
pass_security=\\nt_server_ip_address
```

where `nt_server_ip_address` is the IP address of the primary password server.
All of the other `pass_security` lines should be commented out.

Change the LAN Manager authentication security level on Windows PC:

Administrative Tools

- Local Security Policy

 - Local Policies

 - Security Options

 - Network security: LAN Manager authentication level:

 - Send LM & NTLM - use NTLMv2 session security if negotiated

Registry entry if Microsoft Windows Home Edition:

```
[HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\Lsa]
"LmCompatibilityLevel"=dword:00000001
```

Apply change and then reboot Windows computer.

Print to Shared Printer Connected to Windows PC:

Remote printing no longer works "out of the box" with Windows. Changes need to be made to allow connections from the UNIX server to the shared printer. This also applies to connecting to shares with FacetWin's fct_client utility. To change the LAN Manager authentication security level on Windows:

Administrative Tools

Local Security Policy

Local Policies

Security Options

Network security: LAN Manager authentication level:

Send LM & NTLM - use NTLMv2 session security if negotiated

The change to disable digitally signed communications:

Administrative Tools

Local Security Policy

Local Policies

Security Options

Microsoft Network: Digitally sign communications (always): Disabled

Apply change and then reboot Windows PC.